



STEALTHtip #2

Q&A Tip: The StealthAUDIT Instant Job Library houses pre-canned jobs and solution sets.

Q: Where are the pre-configured jobs located in StealthAUDIT?

A: Pre-configured jobs are referred to as Instant Jobs. Instant Jobs are housed in the Instant Job Library. The Instant Job Library is accessible by right-clicking the Jobs folder in StealthAUDIT and selecting 'Add Instant Job' or by clicking the first icon on the toolbar.

Q: How do I find jobs in the Instant Job Library?

A: The instant Job Library consists of categories. Each category contains jobs relative to the job's function. To find a specific job, determine the function of the job, navigate to the category that best matches the audit scope, expand the category and scroll through the listing.

Q: How do I instantiate an Instant Job from the Library into my job tree?

A: To instantiate Instant Jobs from the library to the Job tree perform the following from the Instant Job Library:

- Navigate to the category containing the job, expand it
- Scroll through the job listing and select the desired job, click Next
- Select a pre-configured host list or add a host name manually in the Host Name text box, click Next
- Click one of the following options:
 - Save & Exit: Clicking Save & Exit will retain your host list assignment and instantiate the job into the job tree
 - Save & Run Job Now: Save & Run Job Now retains your host list assignments, instantiates the job into the job tree, and executes the job

Q: Can I instantiate multiple jobs from the Instant Job library at the same time?

A: Only solution sets containing multiple jobs can be instantiated from the Instant Job Library into the job tree at any one time. The solution sets are found in the Instant Job Library under the Instant Solution category. Multiple jobs can be extracted from the Instant Job Library directory and placed into your Job tree manually. Instant Jobs can be found in the file system in the following location: %programfiles%\Stealthbits\StealthAUDITv4\InstantJobs.

To manually move jobs from the file system to your jobs directory, perform the following:

- Enter the InstantJobs directory within the file system
 - For typical installations, the InstantJob directory is located: %programfiles%\Stealthbits\StealthAUDITv4\InstantJobs
- Navigate to the directory of the category containing the desired jobs
- Select and copy desired jobs
 - Job directories are prefaced with "JOB_"; e.g., JOB_MAY07_MS07-029_DNS_PatchCheck
- Paste the copied jobs to your Jobs directory
 - For typical installations, the jobs directory is located: %programfiles%\Stealthbits\StealthAUDITv4\Jobs
 - Note: You can create a custom job group in the file system by creating a new folder and changing the name to match the naming convention for groups. Group folders must start with "GROUP_"; e.g., GROUP_MY_Group.
- If StealthAUDIT was open during this process, right-click the Job tree and select refresh; your jobs will appear.

Q: Can I create my own Instant Job Library Category?

A: Yes. To create a custom Instant Job Library category, perform the following:

- From within the InstantJob directory in the file system, create a folder prefaced with "IJ_"; e.g., IJ_My_InstantJob_Category
- Copy and paste job directories to this location
- Note: Job directory names are prefaced with "Job_"
- Jobs can now be accessed through the Instant Job Library Wizard

For additional troubleshooting tips and information email support@STEALTHbits.com.

